DragonSpeechTips

Useful Built-in Dragon Commands for Emulating Keyboard Keys, Moving the Mouse Pointer, MouseGrid and Generic commands

Keyboard

Command(s) you can say	Description
Press Enter Press Return	Presses the keyboard Enter (Return) key.
Press Space Press Space Bar	Presses the keyboard Space Bar.
Press up arrow	Presses the keyboard Up Arrow key.
Press down arrow	Presses the keyboard Down Arrow key.
Press left arrow	Presses the keyboard Left Arrow key.
Press right arrow	Presses the keyboard Right Arrow key.
Press Tab	Presses the keyboard Tab key.
Press Delete	Presses the keyboard Delete key.
Press Backspace	Presses the keyboard Backspace key.
Press Control <key>	Holds down the Control key and presses the dictated key. For example, say "press control A"
Press Alt <key>	Holds down the Alt key and presses the dictated key. For example, say "press alt F4"

Accessing Application Menus commands

Command(s) you can say	Description
Click <menu name>	By dictating the word "click" followed by the name of the menu (e.g. "Click Insert"), Dragon will reveal the "Insert" menu of the application ready for you to dictate and choose one of the menu options.
Click <menu option>	By dictating the word "click" followed by the name of the menu option, Dragon will carry out the menu option.

Cut, Copy, Paste and Undo commands

Command(s) you can say	Description
Cut that	Removes the selected text or object to the Clipboard.
Copy that	Copies the selected text or object to the Clipboard.
Paste that Paste the selection	Pastes the contents of the Clipboard.
Undo that	Undoes the last command or action, emulates the keyboard key combination Ctrl + Z.
Delete that	Removes the last dictated word or phrase.

MouseGrid commands

Command(s) you can say	Description
Mouse grid	Reveals the numbered areas of the Mouse Grid.
Mouse grid window	Reveals the numbered areas of the Mouse Grid within the active window.
Whilst the Mouse Grid is in view <number>	The pointer will move to the dictated number (1-9) area. A smaller grid will be redrawn within the dictated number area.
Go Cancel	Closes the Mouse Grid.
Mouse grid <number><number><number>	To quickly navigate to a specific area on the screen. For example, say "mouse grid 5 5 5"
Undo that	Dragon will undo the last MouseGrid action
Whilst the MouseGrid is in view Mark	By dictating the word "mark" when the pointer is over an object you want to move, Dragon will select the object and close the grid.
Whilst the MouseGrid is in view Drag	Re-open the MouseGrid and say a number to select the intended area for the object to be moved to. By dictating the word "drag", Dragon will drag the marked object to the new area and close the grid.

Moving the Pointer and Mouse Actions

Command(s) you can say	Description
Mouse click	Clicks the mouse button.
Mouse double click	Double clicks the mouse button.
Mouse right click	Clicks the mouse right button.
Move mouse up Move mouse down Move mouse left Move mouse right Move mouse upper left Move mouse upper right Move mouse lower left Move mouse lower right	Dragon will start to move the mouse pointer in the direction dictated.
Drag mouse up Drag mouse down Drag mouse left Drag mouse right Drag mouse upper left Drag mouse upper right Drag mouse lower left Drag mouse lower right	Dragon will start to drag the mouse pointer in the direction dictated.
Faster	By dictating the word "faster" while the pointer is moving, Dragon will increase the rate of movement.
Slower	By dictating the word "slower" while the pointer is moving, Dragon will decrease the rate of movement.
Much Faster	By dictating the word "much faster" while the pointer is moving, Dragon will significantly increase the rate of movement.
Much Slower	By dictating the word "much slower" while the pointer is moving, Dragon will significantly decrease the rate of movement.
Stop	Stops the moving mouse pointer.

DragonSpeechTips.com

info@dragonspeechtips.com