# **D**ragonSpeechTips

### 380<sup>+</sup> Custom Dragon Commands for Dolphin SuperNova Magnifier & Screen Reader Edition

#### **Details**

Dragon by default does not provide you with voice commands to carry out most of the SuperNova Magnifier & Screen Reader Edition functions and as such you will find that you are limited to the built-in menu and key press Dragon commands.

The following Dragon commands have been created by DragonSpeechTips (DST) to provide a wealth of additional voice commands that can be dictated when using SuperNova Magnifier & Screen Reader Edition.

#### File functions

C	Desmination
Command(s) you can say	Description
show supernova control panel supernova control panel show supernova	Shows/reveals the SuperNova control panel. The SuperNova application must be already running.
hide supernova control panel hide supernova hide control panel	Hides the SuperNova control panel. The SuperNova application must be already running.
change keyboard settings keyboard settings	Opens the Choose Keyboard and Hotkey window.
change hot key settings hot key settings	Opens the Hot Keys Desktop (101 or more keys) Defaults Number Pad window.
new situation settings create new situation settings open new situation settings window	Opens the New Situation Settings window.
new application settings create new application settings create a new settings file use an existing settings file open new application settings window	Opens the New Application Settings window.
new map file create a new map file create new map file use an existing map file open select map file window	Opens the Select map file window
edit situation settings open situation settings open situation management window	Opens the Situation Management window.
edit application settings open application settings open settings file management window	Opens the Settings File Management window.
edit map file settings edit map settings open map file management window open map settings	Opens the Map file Management window.
<pre>import application settings import application settings file</pre>	Opens the Import window (looking for Dolphin Atlas files).
import map import map file	Opens the Import window (looking for Dolphin Map files).

### File functions (cont'd)

Command(s) you can say	Description
<pre>import script import script file</pre>	Opens the Import window (looking for Dolphin Script files).
import user settings import user settings file	Opens the User Settings Import window (looking for Dolphin Settings files).
export application settings export application settings file	Opens the Browse for Folder window (ready for you to select the intended destination).
export map export map file	Opens the Select map file to export window.
export script export script file	Opens the Browse for Folder window (ready for you to select the intended destination).
export user settings export user settings file	Opens the User Settings Export window (ready to save a Dolphin Settings file).
open profiles window open the profiles window	Opens the Profile window.
restore global preferences	Opens the Restore Dolphin Defaults window (confirm to restore to the Dolphin defaults).
restore all maps and scripts restore maps and scripts	Opens the Restore all maps from Defaults window (confirm to restore to the Dolphin defaults).
restore default settings restore defaults	Reveals the Restore Defaults menu options.
save settings save all settings	Saves the current Dolphin SuperNova settings.
exit supernova quit supernova	Quits the Dolphin SuperNova application.

# Magnifier and Screen functions

Command(s) you can say	Description
magnifier on	
magnifier view	
turn magnifier on	Turns on the Magnifier View
turn on magnifier view	
turn on magnifier	
magnifier off	
turn magnifier off	Turns of the Magnifier view
turn off magnifier	Turns of the magnifier view
turn off magnifier view	
full screen view	Switches the current Magnifier View to the Full Screen magnifier view.
switch to full screen view	Switches the current magnifier view to the run screen magnifier view.
fixed window view	Switches the current Magnifier View to the Fixed Window magnifier
switch to fixed window view	view.
magnifying glass view	Switches the current Magnifier View to the Magnifying Glass magnifier
switch to magnifying glass view	view.
resizing glass view	Switches the current Magnifier View to the Resizing Glass magnifier view.

# Magnifier and Screen functions (cont'd)

Command(s) you can say	Description
toggle view <sup>3</sup>	Switch to the next Magnifier View type, repeat again to change to the
change view <sup>3</sup>	next of the Magnifier views.
increase magnification <sup>3</sup>	
zoom in <sup>3</sup>	Increases the magnification level.
larger <sup>3</sup> make larger <sup>3</sup>	
decrease magnification <sup>3</sup>	
zoom out <sup>3</sup>	Degrees the magnification level
smaller <sup>3</sup>	Decreases the magnification level.
make smaller <sup>3</sup>	
pan left <sup>1,3</sup>	Pans the screen to the left.
pan to the left <sup>1,3</sup> pan right <sup>1,3</sup>	
pan to the right <sup>1,3</sup>	Pans the screen to the right.
pan up <sup>1,3</sup>	Pane the cerean unwards
pan upwards <sup>1,3</sup>	Pans the screen upwards.
pan down <sup>1,3</sup>	Pans the screen downwards.
pan downwards <sup>1,3</sup>	
apply left split screen view	Switches the current Magnifier View to the Left Split Screen magnifier
left split screen view	view.
apply right split screen view	Switches the current Magnifier View to the Right Split Screen magnifier
right split screen view	view.
apply top split screen view	Switches the current Magnifier View to the Top Split Screen magnifier
top split screen view	view
top spire sereen view	TICHT
apply bottom split screen view	Switches the current Magnifier View to the Bottom Split Screen
bottom split screen view	magnifier view.
move application right between monitors <sup>1</sup>	When a user has two screens, it moves the selected application window
move application to the right monitor <sup>1</sup>	on the left monitor to the right monitor.
move application left between monitors <sup>1</sup>	When a user has two screens, it moves the selected application window
move application to the left monitor <sup>1</sup>	on the right monitor to the left monitor.
The command is available only on Desktop (101 or mo.	

### **Visual functions**

Command(s) you can say	Description
open mouse pointers window change mouse pointer	Opens the Mouse Pointers window.
open doc reader settings window change doc reader settings window	Opens the Doc Reader Settings window.
advanced visual options visual advanced options window visual advanced options	Opens the Visual Advanced Options window.
colour scheme on turn on colour scheme	Turns on the SuperNova Colour Scheme option.
colour scheme off turn off colour scheme	Turns off the SuperNova Colour Scheme option.

# Visual functions (cont'd)

Command(s) you can say	Description
colour scheme one <sup>4</sup>	Changes the screen to the Invert Brightness colour scheme.
invert brightness <sup>4</sup>	J
colour scheme two <sup>4</sup>	
apply negative colour scheme <sup>4</sup>	Changes the screen to the Negative colour scheme.
change to negative colour scheme <sup>4</sup>	
negative colour scheme <sup>4</sup>	
colour scheme three <sup>4</sup>	
greyscale colour scheme <sup>4</sup>	Changes the screen to the Greyscale colour scheme.
apply greyscale colour scheme <sup>4</sup>	g
change to greyscale colour scheme <sup>4</sup>	
colour scheme four <sup>4</sup>	
apply high contrast white on black <sup>4</sup>	Changes the screen to the High Contrast White on Black colour scheme.
apply high contrast white on black colour	
scheme <sup>4</sup>	
colour scheme five <sup>4</sup>	
apply high contrast black on white <sup>4</sup>	Changes the screen to the High Contrast Black on White colour scheme.
apply high contrast black on white colour	
scheme <sup>4</sup>	
colour scheme six <sup>4</sup>	
apply yellow on blue <sup>4</sup>	Changes the screen to the Yellow on Blue colour scheme.
apply yellow on blue colour scheme <sup>4</sup>	
colour scheme seven <sup>4</sup>	
apply green on black <sup>4</sup>	Changes the screen to the Green on Black colour scheme.
apply green on black colour scheme <sup>4</sup>	
colour scheme eight <sup>4</sup>	
apply white on blue <sup>4</sup>	Changes the screen to the White on Blue colour scheme.
apply white on blue colour scheme <sup>4</sup>	
colour scheme nine <sup>4</sup>	
apply white on green <sup>4</sup>	Changes the screen to the White on Green colour scheme.
apply white on green colour scheme <sup>4</sup>	
colour scheme ten <sup>4</sup>	
apply red on black <sup>4</sup>	Changes the screen to the Red on Black colour scheme.
apply red on black colour scheme <sup>4</sup>	
colour scheme eleven <sup>4</sup>	
apply red white and blue <sup>4</sup>	Changes the screen to the Red, White and Blue colour scheme.
apply red white and blue colour scheme <sup>4</sup>	
colour scheme twelve <sup>4</sup>	
apply blue yellow and black <sup>4</sup>	Changes the screen to the Blue, Yellow and Black colour scheme.
apply blue yellow and black colour	changes the sereen to the blue, renow and black colour scheme.
scheme <sup>4</sup>	
colour scheme thirteen <sup>4</sup>	Changes the screen to the Emerald colour scheme.
apply emerald colour scheme <sup>4</sup>	changes the serven to the Emerald colour scheme.
colour scheme fourteen <sup>4</sup>	
apply yellow on black⁴	Changes the screen to the Yellow on Black colour scheme.
apply yellow on black colour scheme⁴	
colour scheme fifteen <sup>4</sup>	Changes the screen to the Stormy Skips colour schome
apply stormy skies colour scheme <sup>4</sup>	Changes the screen to the Stormy Skies colour scheme.
colour scheme sixteen <sup>4</sup>	
apply green screen <sup>4</sup>	Changes the screen to the Green Screen colour scheme.
apply green screen colour scheme <sup>4</sup>	
colour scheme seventeen <sup>4</sup>	Channes the severe to the Dive Mach colour selection
apply blue wash colour scheme <sup>4</sup>	Changes the screen to the Blue Wash colour scheme.
colour scheme eighteen <sup>4</sup>	
apply pink colour scheme <sup>4</sup>	Changes the screen to the Pink colour scheme.
colour scheme nineteen <sup>4</sup> apply psychedelic colour scheme <sup>4</sup>	Changes the screen to the Psychedelic colour scheme.

#### Visual functions (cont'd)

Visual functions (cont a)		
Command(s) you can say	Description	
colour scheme twenty <sup>4</sup> apply orange colour scheme <sup>4</sup>	Changes the screen to the Orange colour scheme.	
colour scheme twenty one <sup>4</sup> apply blue tint <sup>4</sup> apply blue tint colour scheme <sup>4</sup>	Changes the screen to the Blue Tint colour scheme.	
colour scheme twenty two <sup>4</sup> apply cyan tint <sup>4</sup> apply cyan tint colour scheme <sup>4</sup>	Changes the screen to the Cyan Tint colour scheme.	
colour scheme twenty three <sup>4</sup> apply green tint <sup>4</sup> apply green tint colour scheme <sup>4</sup>	Changes the screen to the Green Tint colour scheme.	
colour scheme twenty four <sup>4</sup> apply red tint <sup>4</sup> apply red tint colour scheme <sup>4</sup>	Changes the screen to the Red Tint colour scheme.	
custom colour scheme <sup>4</sup> apply custom colour scheme <sup>4</sup> apply my custom colour scheme <sup>4</sup> switch to my colour scheme <sup>4</sup>	Changes the screen to the Custom Scheme.	
configure custom colour scheme	Opens the Configure Custom Colour Scheme window. The current colour scheme must be set to the custom colour scheme.	
highlighting on turn on highlighting	Turns on the SuperNova highlighting option.	
highlighting off turn off highlighting	Turns off the SuperNova highlighting option.	
toggle highlighting	Switches SuperNova highlighting from on to off and vice versa.	
default highlighting <sup>5</sup> reset highlighting <sup>5</sup> change to default highlighting <sup>5</sup>	Switches the current highlighting style back to the Default highlighting style.	
large red highlighting <sup>5</sup> switch to large red highlighting <sup>5</sup>	Switches the current highlighting style to the Large Red highlighting style.	
large red with mouse highlighting <sup>5</sup> switch to large red with mouse highlighting <sup>5</sup>	Switches the current highlighting style to the Large Red with Mouse highlighting style.	
large blue highlighting <sup>5</sup> switch to large blue highlighting <sup>5</sup>	Switches the current highlighting style to the Large Blue highlighting style.	
large blue with mouse highlighting <sup>5</sup> switch to large blue with mouse highlighting <sup>5</sup>	Switches the current highlighting style to the Large Blue with Mouse highlighting style.	
large yellow highlighting <sup>5</sup> switch to large yellow highlighting <sup>5</sup>	Switches the current highlighting style to the Large Yellow highlighting style.	
large yellow with mouse highlighting <sup>5</sup> switch to large yellow with mouse highlighting <sup>5</sup>	Switches the current highlighting style to the Large Yellow with Mouse highlighting style.	
highlighting options highlighting settings open highlighting options window	Opens the Highlighting Options window, enabling a user to create a custom highlighting style.	
custom highlighting <sup>5</sup> switch to custom highlighting <sup>5</sup> turn on custom highlighting <sup>5</sup>	Switches the current highlighting style to the Custom highlighting style.	
<sup>4</sup> The command requires the colour scheme option to be switched on		

 $<sup>^{5}</sup>$  The command requires the highlighting option to be switched on, to see the effect

#### Line View functions

Command(s) you can say	Description
line view document <sup>1</sup>	Reveals the Line View of the text of the current document. The Line
line view the document <sup>1</sup>	View starts with the text that is at the beginning of the document.
start line view from cursor	Reveals the Line View of the text of the current document. The Line
start line view	View starts from the cursor position.
start scrolling	Causes the text to start scrolling right to left.
stop scrolling	Stops the scrolling of the Line View text.
scroll faster increase scroll speed increase scrolling speed	Increases the scrolling speed of the Line View text.
scroll slower decrease scroll speed decrease scrolling speed	Decreases the scrolling speed of the Line View text.
skip backward skip backwards	Jumps backwards along the line of text.
skip forward skip forwards	Jumps forwards along the line of text.
skip backward low skip backwards low skip backward medium skip backwards medium skip backward high skip backwards high	Jumps backwards an amount of text along the line of text.
skip forward low skip forwards low skip forward medium skip forwards medium skip forward high skip forwards high	Jumps forwards an amount of text along the line of text.
exit line view close line view	Closes the Line View.

# **Hooked Area functions**

Command(s) you can say	Description
hooked areas on	December of the Health Assess
show hooked areas	Reveals any existing Hooked Areas.
switch on hooked areas	
hooked areas off	
hide hooked areas	Hides any existing Hooked Areas.
switch off hooked areas	
create hooked area	Creates a Hooked Area.
create a hooked area	Cleates a Hooked Alea.
place hooked area	Confirms the Hooked Area.
set hooked area	Commissible Hooked Area.
modify hooked area	Selects a Hooked Area.
edit hooked area	Selects a noukeu Alea.
go to next area	Selects the next Hooked Area.
next hooked area	שלובניט נוופ וופאנ ווטטאפע אופמ.

### Hooked Area functions (cont'd)

Command(s) you can say	Description
delete hooked area	Deletes the selected Hooked Area.
turn foci highlights on	Turns Foci highlights on.
turn foci highlights off	Turns Foci highlights off.
zoom into hooked area increase magnification of hooked area	Increases the magnification level within the selected Hooked Area.
zoom out from hooked area decrease magnification of hooked area	Decreases the magnification level within the selected Hooked Area.
increase x magnification <sup>1</sup> increase the x magnification <sup>1</sup> magnification x increase <sup>1</sup>	Increases and stretches on the <i>x</i> axis the magnification level within the selected Hooked Area.
decrease x magnification <sup>1</sup> decrease the x magnification <sup>1</sup> magnification x decrease <sup>1</sup>	Decreases and squashes on the <i>x</i> axis the magnification level within the selected Hooked Area.
increase y magnification¹ increase the y magnification¹ magnification y increase¹	Increases and stretches on the <i>y</i> axis the magnification level within the selected Hooked Area.
decrease y magnification¹ decrease the y magnification¹ magnification y decrease¹	Decreases and squashes on the <i>y</i> axis the magnification level within the selected Hooked Area.

# Voice/Speech functions

Command(s) you can say	Description
speech on	
turn speech on	Turns on the SunarNova Speech antion
voice on	Turns on the SuperNova Speech option.
turn voice on	
speech off	
turn speech off	Turns off the CunarNova Cheech antion
voice off	Turns off the SuperNova Speech option.
turn voice off	
increase the volume <sup>6</sup>	
increase volume <sup>6</sup>	Increases the speech volume
louder <sup>6</sup>	Increases the speech volume.
turn up voice <sup>6</sup>	
decrease the volume <sup>6</sup>	
decrease volume <sup>6</sup>	Decreeses the speech values
softer <sup>6</sup>	Decreases the speech volume.
turn down voice <sup>6</sup>	
increase speed <sup>6</sup>	
faster <sup>6</sup>	Increases the rate of speed of the speech.
speed up the voice <sup>6</sup>	
decrease speed <sup>6</sup>	
slow down the voice <sup>6</sup>	Decreases the rate of speed of the speech.
slower <sup>6</sup>	

#### Voice/Speech functions (cont'd)

Command(s) you can say	Description
change synthesiser <sup>1,6</sup> next synthesiser <sup>1,6</sup>	Changes the voice to the next synthesiser voice.
change language <sup>1,6</sup> next language <sup>1,6</sup>	Changes the language of the voice.
select a different voice change voice change the voice	Opens the Voice Preferences window.
stop speech <sup>1</sup>	Stops speech.
stop read from here¹	Stops the speech.
open doc reader window²	Opens the Doc Reader window.
close doc reader window close the doc reader window	Closes the Doc Reader window.
time and date <sup>1</sup>	Speaks out loud the current time and date.
battery status¹	Speaks out loud the current laptop/PC battery status.
open voice preferences window open the voice preferences window	Opens the Voice Preferences window.
show voice and language configuration settings show voice and language settings	Opens the Voice Preferences window.
show user defined voices settings show the user defined voices settings	Opens the Voice Preferences window.
show synthesiser configuration settings show the synthesiser configuration settings	Opens the Voice Preferences window.

<sup>&</sup>lt;sup>1</sup> The command is available only on Desktop (101 or more keyboards)

#### **Braille functions**

Command(s) you can say	Description
braille output on	Turns Braille Output on.
braille output off	Turns Braille Output off.
show braille preferences braille preferences	Opens the General Preferences window
braille general announcements	Opens the General Announcements window
braille input routing buttons options	Opens the Input from Display window.
braille input dolphin cursor options	Opens the Input from Display using Dolphin Cursor window.
braille character options	Opens the Characters window.
braille layout options	Opens the Layout options window.
braille status cells options	Opens the Status Cells window.
braille cursor style options	Opens the Cursor Style options window.

 $<sup>^{2}</sup>$  The command is available for laptop keyboards only

<sup>&</sup>lt;sup>6</sup> The command requires the Speech mode to be turned On

### Braille functions (cont'd)

Command(s) you can say	Description
show braille on screen on turn on show braille on screen	Turns on the Show Braille On Screen option.
show braille on screen off turn off show braille on screen	Turns off the Show Braille On Screen option.
set braille verbosity level to minimum	Sets the Braille Verbosity level to the option Minimum.
set braille verbosity level to low	Sets the Braille Verbosity level to the option Low.
set braille verbosity level to medium	Sets the Braille Verbosity level to the option Medium.
set braille verbosity level to high	Sets the Braille Verbosity level to the option High.
braille hooked areas on	Turns on the Braille Hooked Areas option.
braille hooked areas off	Turns off the Braille Hooked Areas option.
show braille advanced options braille advanced options	Opens the Braille Advanced Options window.

# **General functions**

Command(s) you can say	Description
turn off supernova hotkeys <sup>1</sup>	Turns off/deactivates the SuperNova Hotkeys
turn on supernova hotkeys¹	Turns on/enables the SuperNova Hotkeys.
supernova start up preferences start up preferences	Opens the Startup Preferences window.
supernova update settings	Opens the Automatic Update settings window.
supernova control panel settings	Opens the Control Panel Settings window.
supernova web settings	Opens the Web Page Settings window.
supernova touch screen settings	Opens the Touchscreen window.
supernova feedback settings	Opens the Feedback Settings window.
supernova advanced options	Opens the General Advanced Options.
scan from file scan from a file	Opens the Open file to scan from window.
scan from scanner scan from the scanner	
open scan and read settings open supernova scanner settings	Opens the Scan And Read Settings window.
setup supernova scanner setup the supernova scanner	Opens the Scan And Read Settings window.
select the supernova scan language	Opens the Scan And Read Settings window.
where are my supernova scans located where are my scanned supernova documents	Opens the Scan And Read Settings window and shows the directory path to the Scan and Read Output Folder
show my books	Opens the Bookshelf-online window (My Books).
<sup>1</sup> The command is available only on Desktop (101 or more keyboards)	

#### General functions (cont'd)

Command(s) you can say	Description
show my newspapers	Opens the Bookshelf-online window (Newspapers).
open file in reader	Opens the Open Dolphin Doc Reader file window.
show online books	Opens the Bookshelf-online window (Select Content Provider).
show supernova news	Opens the News window.
supernova radio stations	Opens the Radio Stations window.
supernova podcasts	Opens the Podcasts window.

#### Note:

Dragon generic, menu, keyboard and mouse commands are available for use in Dolphin Supernova and at times should be used with these custom commands.

When performing dictation, the "Dictation Box" may appear and the use of commands such as "Click Transfer" and "Click Cancel" work in the normal way.

For a list of useful Dragon generic commands visit:

https://dragonspeechtips.com/dragon-generic-keyboard-and-mouse-commands/

#### Footnote:

- <sup>1</sup> The command is available only on Desktop (101 or more keyboards)
- <sup>2</sup> The command is available for laptop keyboards only
- <sup>3</sup> The command requires the magnifier view to be switched on
- <sup>4</sup> The command requires the colour scheme option to be switched on
- <sup>5</sup> The command requires the highlighting option to be switched on, to see the effect
- <sup>6</sup> The command requires the Speech mode to be turned On